

**DESCRIPTION:**

Installation: TIGA Software (diskette or from network) is installed on C:\TIGA using the SETUP.BAT supplied.

Before setting up the driver, you must set a SET for the TIGA driver in AUTOEXEC.BAT, e.g. SET TIGA=-mC:\TIGA\ -IC:\TIGA -i0x60

The TIGA driver must be started before loading Windows, using the command C:\TIGA\TIGACD either in C:\AUTOEXEC.BAT or in \WINDOWS\WINSTART.BAT.

Now load WIN 95 and select as follows in the Control Panel:

"Add New Hardware",

"Next"

"Install specific Hardware",

"Display adapters",

"Next"

"Have Disk"

in 'Copy manufacturer's files from:' you set "C:\TIGA\WIN31\OEMSETUP.INF".

Acknowledge all other items with "OK" or "Next" and then reboot.

The resolution can be set using C:\TIGA\TIGAMODE. Then reboot.

The TIGA drivers V2.2 are in the file "Tigav22.exe"